



NetBrain[®] Integrated Edition 10.0

How to Remove Devices from Domain

How to Remove Devices from Domain

Customer Use Case

Some invalid devices exist in a domain, and users want to remove them from the domain to save more license nodes.


Challenge

How to remove devices from a domain?

NetBrain Best Practice

NetBrain provides many ways to remove devices from a domain, and the user can select either of the following ways to remove devices:

- **Remove the device from Site pane**




- 1) Click **Site** on the taskbar.
- 2) Right-click the target device and select **Remove from Domain** from the drop-down list.

- **Remove the device from Device Group**

- 1) Click the target device group and all the devices in this group are displayed in the left pane.
- 2) Right-click the target device and select **Remove From Domain** from the drop-down list.

3) In the pop-up dialog. Click **Yes**.




Note: You can also right-click the target device group and select **Delete** to delete the device group.

Tip: The devices in the **System** folder cannot be removed in this way.

▪ Remove device from Fine Tune

- 1) Log in to Domain Management page.
- 2) In the Domain Management page, click **Operations > Fine Tune** from the quick access toolbar.
- 3) On the **Fine Tune** tab, there are two ways to remove a device:
 - Click **Missed Devices**, and right-click the target device in the table and select **Remove from Domain**.



- Click one device category under **SNMP-Only Devices**, and right-click the target device in the table and select **Remove from Domain**.

Start Page Fine Tune Discover Refresh

Items: 6 Fully CLI-Accessed Rate: 73%

Hostname	Management IP	Device Type	SysObjectID
Multicast-MGMT	172.25.8.15	Cisco IOS Switch	1.3.6.1.4.1.9.1.1227
NATT-ISP	172.25.114.4	Cisco Router	1.3.6.1.4.1.9.1.1
NATT-MGMT	172.25.114.4	Cisco Router	1.3.6.1.4.1.9.1.1227
NATT-NATT	172.25.114.4	Cisco Router	1.3.6.1.4.1.9.1.1
NATT-R1	172.25.114.4	Cisco Router	1.3.6.1.4.1.9.1.1
NATT-R2	172.25.114.4	Cisco Router	1.3.6.1.4.1.9.1.1

Context Menu Options:

- Shared Device Settings
- Network Settings
- Add to Device Group
- Move Selected IPs to Do-Not-Scan IP List
- Remove from Domain**
- Discover Selected Device(s)
- Live Access Log

▪ Delete devices from Fine Tune result

- 1) Log in to Domain Management page.
- 2) In the Domain Management page, click **Operations > Advanced Tools > Tune Live Access** from the quick access toolbar.
- 3) On the **Tune Live Access** tab, open the fine tune result table, check the box and right-click the target device to select **Remove from Domain**.

Start Page Tune Live Access

Check the reachability of live devices using the credentials defined in Network Settings.

All Devices Device Groups All Device Groups, My ... Start Tuning Options Network Settings

Device Name	Management IP	Management Interface	Ping	SNMP RO	SysObjectID	Telnet/SSH
!@#\$%^&*()_-=+~						
.EMU_NAT_R11						
11						
5101_Router						
ASA						
ASA.Router						
ASA-AA/act						
ASA-AA/admin/a						

Context Menu Options:

- Select All
- Unselect All
- Shared Device Settings
- Discover Selected IP
- Remove from Domain**
- Export Selected Device IP
- Add to Device Group
- Clear Results
- Clear All Results
- Export Results
- Load Last Results
- Lock Shared Device Settings